

Transfer Softlock with RUS Tool


Please download the RUS tool first.

<http://download.dlubal.com/?file=RUS.exe>

Target PC = NEW PC

Source PC = OLD PC (with active Softlock)

1. Run tool RUS.exe on the **target PC**. Select the tab *Transfer License* in the RUS dialog box.



RUS

Collect Status Information | Apply License File | **Transfer License**

To transfer (rehost) a license from one computer to another, you run the RUS program on both computers. On each computer, select the **Transfer License** tab and perform the appropriate step.

Collect information about the recipient computer

Step 1: On the computer to which you want to transfer the license (the "recipient computer"), collect and save information about the computer.

Save recipient information to ...

Collect and Save Information

Generate the license transfer file

Step 2: On the computer that currently contains the license (the "source computer"), select the license to transfer, read the recipient information file and generate a license transfer file.

Key Type	Key ID	Products


Read the recipient information file from ...

Generate the license transfer file to ...

Generate License Transfer File

2. Specify path of the output *.id file with recipient information and click on the button *Collect and Save Information*.

3. Run tool RUS.exe on the **source PC** and select the tab *Transfer License*.



Collect Status Information | Apply License File | **Transfer License**

To transfer (rehost) a license from one computer to another, you run the RUS program on both computers. On each computer, select the **Transfer License** tab and perform the appropriate step.

Collect information about the recipient computer

Step 1: On the computer to which you want to transfer the license (the "recipient computer"), collect and save information about the computer.

Save recipient information to ...

Generate the license transfer file

Step 2: On the computer that currently contains the license (the "source computer"), select the license to transfer, read the recipient information file and generate a license transfer file.

Key Type	Key ID	Products
SL-AdminMode	XXXXXXXXXXXXXXX	

Your active softlock

File created from source PC

Read the recipient information file from ...

Generate the license transfer file to ...

4. Select the SL license you want to transfer.

5. Read the recipient information file (*.id). Specify the location of the output license transfer file (*.h2h).
Click the button *Generate License Transfer File*.

6. Run tool RUS.exe on the target PC and open the tab *Apply License File*.

7. Upload the license transfer file (*.h2h) and click on the button *Apply Update*.

8. Run the Dlupal Software and import the current author.ini file (also possible in DEMO mode) by using Help > Authorization.
After restarting the software, you can use it as a full version.

Your team from DLUBAL SOFTWARE GMBH